

# EXTRACTION CLEANING

## Tools Needed

- Wet Floor Sign
- Carpet Extractor
- Measuring Cup
- Carpet Rake or Stiff Brush



## Product Needed

P&G Pro Line  
Carpet Extraction Cleaner / Sanitizer



**FREQUENCY OF CLEANING:** When carpet looks heavily soiled. Regular bonnet cleaning will extend time between extraction cleaning.

**PREPARATION:** Collect all tools, equipment and products required. Ensure all equipment is operational. Review MSDS, product labels and caution statements. Choose appropriate safety equipment.

**SPECIAL DIRECTIONS FOR THIS TASK:** Pre-test extraction cleaner for colorfastness before use. Do not use if color is removed, faded or otherwise changed. Extraction Cleaner / Sanitizer is recommended for use on washable synthetic fibers. Extraction Cleaner / Sanitizer is not recommended for use on wool or stain resistant carpets. Clear furnishings from area. Protect furnishings that cannot be moved. Replace furnishings when finished. Use furniture pads if furniture must be replaced before floor is dry. When finished, clean and return equipment to storage area.



### STEP 1

- Pre-treat stains following the Spot, Stain, Gum Removal Procedure.
- Remove grit and loose soil by following the Vacuum Procedure.
- For heavily soiled carpets, bonnet clean area following the Bonnet Cleaning Procedure or the Bonnet Cleaning – Immersion Method Procedure.



### STEP 2

- Post "wet floor" sign in area to be cleaned.  
**NOTE: Pre-test extraction cleaner for colorfastness before use. Do not use if color is removed, faded or otherwise changed.**

**NOTE: Extraction Cleaner / Sanitizer is not recommended for use on wool or stain resistant carpets.**

### STEP 3

- Fill extraction tank to just below fill line.
- Add 10 ounces extraction.
- Add 1 ounce foam control.
- Slowly add water until solution level reaches the fill line.

**NOTE: Proper dilution of extraction cleaner is 2 ounces per 1 gallon tank capacity. Proper dilution of foam control agent is 1 ounce per 5 gallon tank capacity.**

### STEP 4

- Begin extracting at farthest point from door.
- Moving in a constant steady motion, hold feed valve open and pull extractor towards you.
- Release the feed valve before reaching end of pass.
- With control valve closed, push extractor forward to pick-up moisture and soils.

**NOTE: Avoid overwetting carpet.**



### STEP 5

- Move to next section, working towards doorway and repeat Step 4 through Step 5.



### STEP 6

- Empty and rinse tank and.
- Fill tank with hot water to rinse area.
- Moving in a constant steady motion, hold feed valve open and pull extractor towards you.
- Release the feed valve before reaching end of pass.
- With control valve closed, push extractor forward to pick up rinse water.

**NOTE: Avoid overwetting carpet.**

### STEP 7

- Brush or rake carpet in one direction to set nap up.



### STEP 8

- Apply Carpet / Upholstery Protectant following the Carpet/Upholstery Protection Procedure.

**NOTE: Carpet / Upholstery Protectant may be applied while carpet is wet.**

### STEP 9

- Vacuum carpet when dry following the Vacuum Procedure.



**NOTE: To speed dry carpet, buff with clean dry bonnets, turning and changing often. A fan may be used. Direct air movement up across or out from room.**