

BONNET CLEANING – IMMERSION METHOD

Tools Needed

- Wet Floor Sign
- 175- 300 RPM Floor Machine with Bonnet Holder
- Bonnet Pads
- 1 gallon sprayer
- Measuring Cup
- 2 Mop Buckets with Wringer



Product Needed

P&G Pro Line
Carpet Spot Remover, Traffic Lane /
Bonnet Cleaner & Extraction Cleaner



FREQUENCY OF CLEANING: Weekly or monthly to clean top fiber sections of carpet. Carpet will look slightly soiled from oily soils attached to top portion of carpet fibers


PREPARATION: Collect all tools, equipment and products required. Ensure all equipment is operational. Review MSDS, product labels and caution statements. Choose appropriate safety equipment.

SPECIAL DIRECTIONS FOR THIS TASK: Pre-test for colorfastness before use. Do not use if color is removed, faded or otherwise changed. Clear furnishings from area. Protect furnishings that cannot be moved. Replace furnishings when finished. Use furniture pads if furniture must be replaced before floor is dry. When finished, clean and return equipment to storage area.



STEP 1

- Pre-treat stains following the Spot, Stain, Gum Removal Procedure.
- Remove grit and loose soil by following the Vacuum Procedure.




STEP 2

- Post "out of service" sign in area to be cleaned.

NOTE: Pre-test cleaner for colorfastness before use. Do not use if color is removed faded or otherwise changed.


STEP 3

- Fill 1 gallon sprayer with water until level reaches $\frac{3}{4}$ full.
- Add 14 ounces of traffic lane/bonnet cleaner.
- Slowly add water until solution level reaches the 1 gallon fill line.




STEP 4

- Fill 1 mop bucket with 2 gallons of water.
- Add 32 ounces of bonnet cleaner.
- Fill 2nd mop bucket with 2 gallons of water.




NOTE: 2nd mop bucket will be used to rinse bonnet pads as needed.




STEP 5

- Start at farthest point from door, working in a 10 ft. by 10 ft. area.
- Hold 1 gallon spray nozzle 12 inches from carpet.
- Apply solution in even, overlapping strokes on localized traffic lane and other highly soiled localized areas.



STEP 6

- Submerge bonnet in bonnet cleaner solution.
- Wring bonnet as dry as possible.
- Buff area, moving machine left to right, overlapping each pass..



STEP 7

- Move to next 10 ft. by 10 ft. area, working towards doorway and repeat Step 5 through Step 7.

NOTE: Turn bonnet pad over as the pad becomes soiled. Rinse dirty bonnet in clean water. Wring pad as dry as possible. Use new bonnet as needed.

STEP 8

- Vacuum carpet when dry following the Vacuum Procedure.



NOTE: To speed dry carpet, buff with clean dry bonnets, turning and changing often. A fan may be used. Direct air movement up across or out from room.